

Priority Alert Control

The DEVOS system provides web page control of Priority Alerts. Using the web page, you can easily create, edit, remove, and activate or cancel a Priority Alert. You can also activate a Priority Alert using an API or by using the Priority Alert Desktop control.

Desktop Control

The desktop control provides immediate activation of an alert without needing to access the system in a browser, log in, navigate to the alert, and press a confirm an alert button. In an emergency, the desktop button can save valuable time. While the desktop button has no security features (anyone can press it), we presuppose it is only available on an authorized Windows computer where the user has already been authenticated.

Setting About		
Offic	ce Camera	
riority Alert Setting DEVOS Server yourserver		>
Title	Code	Double-Click
WTNH 2 Minutes Web Time MAAVRO Streamie Live Paking Lot Diffee Camera CNN	51 c53a20844 33e3d569411 0547c4474a97 11 eb128844a 226d251a31b6 34c6cd70694	To Select Right-Click To Remove
Control+Shift+Home C Co Control+Shift+F3 C Co	t and copy the code from the URL aft ontrol+Shift+F1 C Control+Shift ontrol+Shift+F4	
Require 5 Times		
You may also trigg	er the alert using the selected	kevs above

Install the program and launch it from the windows start menu. Select Settings. Enter your DEVOS server address. If your server has a certificate, you may check "SSL". Log in to DEVOS, find a Priority Alert, and select edit. Copy the code from the browser after the "&pag=" and before "&o=".



Application Note

Paste this code into the app and enter a name. Press "Add" to add it to your list. Repeat for each potential Priority Alert you wish to use.

Double-Click on any Title in the list to make the button refer to this alert. Notice the button changes to the title.

Click on the button to trigger the alert.

You may also select certain keys to trigger the alert (e.g. Control+Shift+Home). To prevent false alerts from keys, you may select "Require 5 Times", which will cause the alert to be triggered only if the selected keys are pressed 5 times.

Please note that the desktop control does not use the Priority Alert duration. When you trigger an alert, it will be active for the configured duration of the alert. The desktop program button will turn red for 1 minute regardless of the configured duration. The desktop program cannot cancel an alert.

About Priority Alert

The DiscoverVideo Priority Alert will cause a live video, a VoD video, a text message, or a web page, to appear on one, some, or all Windows or Mac computers without user action. The Priority Alert will also appear on one, some, or all SignSticks and Set Top Boxes. The Priority Alert may also send text messages to list of cell phone numbers.